

Control coordinates of robotic arm end

1. About code

Path code: ~/jetcobot_ws/src/jetcobot_ctrl/scripts/ctrl_coords.ipynb

Create three new buttons to control the robotic arm reset, enable, and uninstall functions.

```
def on_button_clicked(b):
    with output:
        print("Button clicked:", b.description)
    if b.description == 'Reset':
        reset_joints()
    elif b.description == 'Power_on':
        mc.power_on()
        b.icon = 'check'
        button_power_off.icon = 'uncheck'
    elif b.description == 'Power_off':
        mc.power_off()
        b.icon = 'check'
        button_power_on.icon = 'uncheck'
```

Create seven new sliders to control the six parameters of the robot's coordinates and the gripper.

```
def on_slider_gripper(angle):
    print("G7:", angle)
    mc.set_gripper_value(angle, g_speed)

def on_slider_coords(x, y, z, rx, ry, rz):
    coords = [x, y, z, rx, ry, rz]
    mc.send_coords(coords, g_speed, 0)
```

Create a new slider to control the movement speed of the servo.

```
slider_speed = widgets.IntSlider(description='Speed:', value=50, min=1, max=100,
step=1, orientation='horizontal')

def on_slider_speed(value):
    global mc, g_speed
    g_speed = value
    print("speed:", value)

widget_speed = widgets.interactive(on_slider_speed, value=slider_speed)
```

Reset the joint angles of the robotic arm.

```
def reset_joints():
    if button_power_off.icon == 'check':
        mc.power_on()
```

```

        time.sleep(1)
    mc.send_angles([0, 0, 0, 0, 0, -45], 50)
    mc.set_gripper_value(100, 50)
    slider_x.value = 50
    slider_y.value = -64
    slider_z.value = 419
    slider_rx.value = -90
    slider_ry.value = -45
    slider_rz.value = -90
    slider_g.value = 100
    slider_speed.value = 50
    button_power_on.icon = 'check'
    button_power_off.icon = 'uncheck'

```

Create a camera display window to read the camera image in real time and display it.

```

imgbox = widgets.Image(format='jpg', width=640, height=480,
layout=widgets.Layout(align_self='center'))
model = 'Start'

```

```

def camera():
    global model
    capture = cv.VideoCapture(0)
    capture.set(cv.CAP_PROP_FRAME_WIDTH, 640)
    capture.set(cv.CAP_PROP_FRAME_HEIGHT, 480)
    while capture.isOpened():
        try:
            _, img = capture.read()
            if model == 'Exit':
                break
            imgbox.value = cv.imencode('.jpg', img)[1].tobytes()
        except:
            break
    print("capture release")
    capture.release()

```

Create a new end button to end the program and release resources.

```

button_close = widgets.Button(description='Close_Camera', button_style='danger')
def button_close_Callback(value):
    global model
    model = 'Exit'
    with output: print(model)
button_close.on_click(button_close_Callback)

```

2.Run program

Click the Run Entire Program button on the Jupyterlab toolbar and scroll to the bottom.



You can see that the relevant control controls are displayed on the left and the camera display screen is displayed on the right.

